

PAMGuard – Tethys In A Hurry

Douglas Gillespie¹ and Marie Roch²

¹Sea Mammal Research Unit, University of St Andrews

²Department of Computer Science, San Diego State University

2025-03-21

Tutorial Version 1.2

Learning Outcomes

This tutorial assumes you're familiar with both the PAMGuard Viewer and Tethys, have both PAMGuard and Tethys installed and running on your computer, and just need a quick guide to export some data:

1. Add a Tethys module to PAMGuard and connect to the Tethys Server
2. Understand relationships between PAMGuard data and Tethys documents
3. Export data from PAMGuard to Tethys:
 - Calibration data
 - Deployment data
 - Detections
4. View the exported data both from within PAMGuard and using the Tethys Web client
5. Know where to go for help, or if things go wrong

Table of contents

1 Prerequisites	1
1.1 Software Versions	1
1.2 Data	1
1.2.1 Click Classification	1
2 Add the Tethys Module to PAMGuard	1
3 Set Essential PAMGuard Metadata	1
4 Export Calibration information	2
4.1 Set Values in PAMGuard	2
4.2 Run the Export Wizard	3
5 Export Deployment data	5
6 Export Detections	5
6.1 Species Codes	5
6.2 Granularity	7
6.3 Run The Export Wizard	7
7 View your data in PAMGuard	9
7.1 Web Client	9
7.2 PAMGuard Quick View	9
7.3 Delete Exported Documents	10
8 Problems	10
8.1 Problems exporting	10
8.2 PAMGuard viewer not finding Tethys data	11
9 Further Learning	11
9.1 Tethys	11
9.2 PAMGuard Batch Processing	11
10 Acknowledgements	11

List of Figures

1 Tethys server errors colour the PAMGuard display orange	1
2 Instrument identifying information in the PAMGuard array dialog	2
3 PAMGuard Array management dialogs	4
4 Calibration Export Wizard pages	5
5 Deployment Export Wizard pages	6
6 PAMGuard dialogs for setting species codes	7
7 Detections Export Wizard pages	8
8 Message shown on completion of a successful export	9
9 Example of a Deployment document viewed within PAMGuard	10

List of Tables

1 Essential project information	2
2 Data from the SoundTrap calibration certificate	3

1 Prerequisites

1.1 Software Versions

To run this tutorial you must have PAMGuard version 2.02.16 or later, and Tethys sever Version 3.2 beta 2 or later. The Tethys server must be running on your computer. If you don't have these, or don't know how to set them up, please complete the full PAMGuard Tethys tutorial available at www.pamguard.org/tutorials/tethys.html.

1.2 Data

In principle, you can complete this tutorial with any data you like, so long as those data have been processed with PAMGuard and you are able to open and view the data with the [PAMGuard Viewer](#). Again, if you don't know how to do this, we recommend that you complete the earlier tutorial, [Introduction to Static Monitoring](#).

This tutorial picks up where the Static Monitoring tutorial left off, using the pre-processed data available in the file [viewer.zip available on Zenodo](#). If you've successfully completed that tutorial, you should use the data that you've already processed yourself.

1.2.1 Click Classification

If you've downloaded the viewer data from the [Introduction to Static Monitoring](#) tutorial, then you need to run the click classifier on those data to separate out porpoise clicks. Refer to page 37 of that tutorial and complete the section "Automatic classification" before proceeding here.

2 Add the Tethys Module to PAMGuard

Open the data with the PAMGuard Viewer. If you don't already have it in your PAMGuard configuration, from the *File/Utilities* menu, add the Tethys module.

Go to the Tethys tab in your PAMGuard display. If the top is orange (Figure 1), then it's failed to connect to the server, which means either that the server isn't running (so start it) or PAMGuard is looking at the wrong server address. If you've launched Tethys with it's default address (<http://localhost:9779>), then PAMGuard will have worked. If you changed something in Tethys, then change PAMGuard to match Tethys using the settings button just to the right of the address. Once the server connection is established, PAMGuard will revert to its default grey colour.




Figure 1: Tethys server errors colour the PAMGuard display orange

3 Set Essential PAMGuard Metadata

There are certain bits of information that are required by Tethys and are also used to link to your PAMGuard dataset (a PAMGuard database and binary store) to documents

in Tethys.

1. **Project** The Project name is a requirement of Tethys. The project label is text that helps you organize your data. It is usually used to provide a label for a group of instrument deployments that are related by geographic region, funding source, or purpose, and can serve as a useful filter when querying data. The dropdown box will show a list of all project names already available in the Tethys database you're using. You can select a name from the dropdown list, or press the 'New Project' button to enter the name of a new one. A single Project may be associated with many PAMGuard datasets, for example, when deploying autonomous recorders, PAMGuard will have one dataset per recorder, or you may have multiple vessel based surveys which all form part of the same project, but will probably have one PAMGuard dataset per cruise.
2. **Instrument** The Instrument name is used to link specific Tethys Deployment documents back to a single PAMGuard dataset. The linkage uses both the Instrument name and the date range of the PAMGuard data, on the basis that it's impossible for the same instrument to be in two places at once. If it's not set, then press the **New/Edit** button (which will open the PAMGuard array dialog - Figure 2) and enter the information. The information consists of an instrument type, e.g. something like MARU, or SoundTrap-HF600, and an Id, which should ideally be a manufacturer's serial number. If you don't have a serial number, then write something that can be used to identify the equipment, e.g. Instrument Type: "Home made array", Instrument Id: "2024 Mk 2".


The image shows a software dialog box titled "Pamguard hydrophone array". It contains several input fields. Under the heading "Instrument information", there is a field for "Instrument Type" with the value "MARU" and a field for "Instrument Id" with the value "001". Below this is a section for "Hydrophone" with a table that has two columns and one row, the cell containing the number "0". On the right side of the dialog, there is a vertical list of buttons: "Arr", "Ar", "Hyc", "Id", and "0".

Figure 2: Instrument identifying information in the PAMGuard array dialog

If you're working with the data from the Static Monitoring tutorial, then use the following values for project and instrument (Table 1). The latitude and longitude of the deployment are also given here and will be used in the next step

Table 1: Essential project information

Project	Compass
Instrument Type	SoundTrap HF-300
Instrument Id	738725892
Latitude	56.09678
Longitude	-8.02278

4 Export Calibration information

4.1 Set Values in PAMGuard

Before exporting the calibration data, make sure that it's been correctly set. Go back to the array manager dialog, either from the **New/Edit** button next to the instrument id

on the Tethys display, or from the main PAMGuard menu *Settings / Hydrophone Array* ... (Figure 3a).

! Important

The calibration data may not have been set correctly in data from the earlier tutorial, so you need to check it. When you look at the array data, if it's showing two hydrophones, delete the second of them. Then check the calibration and array location data.

Next, edit the hydrophone data by double clicking on the hydrophone element. (Figure 3b): Enter the type as ST-HF300, the sensitivity as -172.5, and the x,y,z coordinates all as zero.

Close that dialog with the OK button, then go to the 'Streamer', but selecting the one at the top that has a reference of a "Ship GPS Data" and press **Edit**.

Enter a name (though this won't be exported to Tethys), and select the Reference Position as "Fixed Location (moorings and buoys)". Then click on the little menu symbol next to the empty Latitude and Longitude fields and set the correct values for the array location. You'll find it easy to copy and paste the correct values (Table 1) if you select Decimal display at the top of the dialog (Figure 3c).

! Complete Calibration Data

Calibration information is not just about the hydrophone. When dealing with digital data, we also need to know how the amplitude of the numbers in the sound files relate to the voltages in the wire generated by the hydrophone. The hydrophone calibration values we've entered above are only telling us half the story, so it's essential that you also tell PAMGuard how sensitive your recording system was. In PAMGuard this is set as a "Peak-Peak voltage range" in the sound acquisition dialog. For SoundTraps, this should be set to 2. See the SoundTrap manuals from [Ocean Instruments](#) for further information.

4.2 Run the Export Wizard

Once all data in PAMGuard are correct, you can run the export wizard which will create a Tethys document and write it to the database. To start the process, press the **Export** button in the "Instrument Calibration Information" section of the display - that's just under the image of the Tethys Roman mosaic.

You'll then be asked for more information about the calibration process (Figure 4). The calibration was performed using a piston phone calibrator at 250Hz, though we don't know the details of the methodology. Fill in what you can. Table 2 is the information we extracted from the calibration certificate for this instrument.

Table 2: Data from the SoundTrap calibration certificate

Date	14 Jan 2018
Operator	JA
Source Model	CENTER 327
Source Serial	130307390
Frequency	250Hz
Coupler	OIC1

Pamguard hydrophone array

Instrument information

Instrument Type: SoundTrap HF-300

Instrument Id: 738725892

Hydrophone

Hydrophone Id (ADC channel)

Environment

Speed of sound: 1500.0 +/- 0.0 m/s

Array Management

Ok Cancel New Array... Copy... Rename... Import... Export... Delete Help...

Array Configuration

Array: January 1, 1970, 12:00:00 AM UTC

Hydrophone Streamers

Id	Name	x	y	d...	Reference	Locator
0	Com...	0.0	0.0	-0.0	Static moorings...	Threading Stre...

Add ... Edit ... Delete

Hydrophone Elements

Id	x	y	depth	x Err	y Err	dept...	Stre...
0	0.0	0.0	5.0	0.0	0.0	0.0	0

Add... Edit... Delete

Channel Configuration

Audio file folder or multiple files: 96.0kHz, 1 channels, 16 bit

Data Cha...	Hydrophone	Gain	Range	Bandwidth
SW Ch 0 / ...	0	0.0 dB	2.0 Vp-p	0.0-20.0 kHz

Change hydrophone ...

(a) Array dialog information for the SoundTrap tutorial dataset

Edit hydrophone

General info

Hydrophone ID: 0

Streamer: Streamer 0, x=0.0

Hydrophone type: ST-HF300

Hydrophone sensitivity: -172.5 dB re 1V/ μ Pa

Preamplifier gain: 0.0 dB

Coordinates (m)

x: 0.0 +/- 0.0 m (right of streamer)

y: 0 +/- 0.0 m (ahead of streamer)

Depth: 0 +/- 0.0 m (depth below streamer)

Interpolation

☒ Use only the latest value

☐ Interpolate between values

☐ Use the location for the time preceding each data unit

Ok Cancel Help ...

Hydrophone Streamer

Streamer Name: Mooring

Reference Position: Fixed location (moorings and buoys)

Latitude: 56°05.807' N

Longitude: 8°01.367' W

Hydrophone Locator Method

Threading Streamer

Position	Error
x: 0.0 +/- 0.1	
y: 0.0 +/- 0.1	
Depth: -0.0 +/- 0.1	

Sensor: Fixed Value

Interpolation

☒ Use only the latest value

☐ Interpolate between values

☐ Use the location for the time preceding each data unit

Ok Cancel Help ...

Hydrophone array reference position

Unit types: ☒ Degrees, Decimal minutes ☐ Degrees, Minutes, Seconds ☐ Decimal

Latitude: deg. 56 sec. dec min. 5.80680 N

Longitude: deg. 8 sec. dec min. 1.36680 W

Ok Cancel

(b) Correct hydrophone array settings

(c) Corrected streamer information

Figure 3: PAMGuard Array management dialogs




Figure 4: Calibration Export Wizard pages

5 Export Deployment data

A key aspect of Tethys is recording why we collected data, as well as how. This is essential in many studies that might use these data. For example, if recorders were placed in a pseudo random pattern across a study area, they are much more suitable for abundance estimation than recorders that were placed in a known hotspot for a particular species. Being verbose with this information as you export the deployment data is therefore essential if the data are going to be useful in years to come.

These data were collected on a duty cycle of 20 minutes recording each hour. There are therefore over 2000 entries in the recordings period table. Right click on the table and *Select All* from the popup menu to export the whole lot as a single, duty cycled, deployment document. For more complex situations, such as ad-hoc deployments from vessels, see the online help.

Press the **Export** button to start the Deployment Export dialog. Again, you'll be asked for several pages of information about what you were doing and why (Figure 5). The information you need can mostly be copied from the project website at <https://compass-oceanscience.eu/>.

6 Export Detections

Output from each detector in PAMGuard must be exported separately. Available outputs are listed in the lower left panel of the display.

6.1 Species Codes

Before you can export data, you must set [ITIS species codes](#) for the detector data that you're planning to export. To do this, right click on the appropriate row in the table (in this case, we'll pick the SoundTrap Click Detector Clicks) and select *Species Info ...* from the popup menu. Two species should be defined, one for clicks that haven't been classified, and one for porpoise clicks (Figure 6a). If this isn't the case, then you've

Deployment Export

Project Information

Project Name

Compass

Select

New

Region

Scotland

Cruise name

Site

Stanton

Responsible Party

Name

Your name

Organisation

your organisation

Position

Email

your email

Previous

Next

Cancel

Deployment Export

Number of documents

☒ Export a single deployment document for all data

☐ Automatically determine duty cycle and decide automatically

☐ Export separate deployment documents for each ad-hoc recording period

Duty cycle: 00:19:59 on, 00:40:00 off, for 2191 cycles

Data location

Sound Files

Enter location of the sound files here

Database

compass_database_D2_stanton_DG.sqlite3

Binary Store

C:\PAMGuardTraining\SoundTraps\viewer\PAMBinary

Sound Files

Ignore this - it's an artifact of the SoundTrap click detector

Previous

Next

Cancel

(a) Project Information

(b) Deployment Effort

Deployment Export

Description data

Objectives

Copied from
<https://www.sams.ac.uk/science/projects/compass/>
Collaborative Oceanography and Monitoring for
Protected Areas and Species

Abstract

The COMPASS project is a 5 year project, which
will establish a network of oceanographic and
acoustic moorings within and adjacent to
cross-border marine protected areas (MPAs), which

Method

Deployment and analysis of data from bottom
mounted recorders

Previous

Finish

Cancel

(c) Deployment Description

Figure 5: Deployment Export Wizard pages

probably not set up and run the species classifier (Section 1.2.1). For each, press the 'Find' button and enter an appropriate search term (Figure 6b) (e.g. porpoise, cetacean, odontoceti). PAMGuard will search the database for possible matches and display a list of options. Select the species / taxa you want. Then also fill in the Call / Sound type information, which is important for species which have more than one call type (e.g. clicks/ whistles). For further information see the [PAMGuard online help](#);




Figure 6: PAMGuard dialogs for setting species codes


6.2 Granularity

Think about the granularity you want to export data at. This dataset contains over a million clicks, and you probably don't want to export all of them. Might you be better off exporting binned data (counts of detections in a set time interval), or encounter data (counts of detections without a gap between them) ? For this example, we'll export encounter level data with an encounter defined as at least 10 clicks and a 10 minute gap from adjacent encounters.

6.3 Run The Export Wizard

Once the species codes are set, you can press the **Export** button to start the export wizard (Figure 7). The first page pulls information about the detector automatically from PAMGuard. On the second page, you select whether you're exporting Detections or Localizations, the Granularity, and importantly set an optional data filter. The data filter is essential for many PAMGuard detectors, such as the Click Detector, which generally run at quite a high false alarm rate, before using an additional classifier to label the clicks of interest. Press the button next to the Data Selection Filter (red box in Figure 7b) and configure it to only select porpoise clicks¹ (Figure 7c). The settings of the data filter


¹Output from different detectors in PAMGuard often have different properties, so the Data Selection Filter you see will be different for each detector. See the PAMGuard online help for information about data selectors



(a) Detector information

(b) Granularity and filtering

(c) Data Selection Filter



(d) Additional Information

(e) Detector Settings Output

(f) Export progress

Figure 7: Detections Export Wizard pages

will be included in the detector parameters written to Tethys to provide a full record of choices made during the export process.

On the next page (Figure 7d) add further information that will help inform anyone using these data. These fields are similar to those you filled in when exporting the Deployment information (Section 5) but require different information. For example, the Deployment information might contain quite general information along the lines of "Sound Trap deployments to detect small cetaceans", but the analysis so far has only dealt with Harbour Porpoise. Perhaps you configured the detector to only detect buzzes, and not regular clicks, etc. you need to include information about what you actually did with the data, which is different to what MIGHT be done with the data here.

Once you get to the last page, press the **Export Data** button and wait while PAMGuard chugs through, loading a file at a time, extracting the clicks that pass the selection filter, creating Encounters, or Binned Data, and then finally writing the document.

Once the export process is complete, a dialog will show to indicate success and a record will show in the table in the bottom right corner of the display (Figure 8). Note that for this export, by selecting to only export porpoise clicks, and exporting them as encounters, only 616 Detection records were created from a total of 1070555 click in the data.




Figure 8: Message shown on completion of a successful export

7 View your data in PAMGuard

The Tethys Client and Data Explorer offer by far the best and most flexible interface for viewing Tethys data. However, PAMGuard does allow a quick view of exported documents which can be useful to verify that data have exported correctly.

7.1 Web Client

Assuming that the server is running, and PAMGuard is successfully connected to the server, then simply press the **Open Client** button at the top of the display. This will open the Tethys Web Client in your default web browser. To view listings of Documents of a particular type (Calibrations, Deployments, etc.), to the small menu in the very top right of the web page, to the right of the Tethys mosaic image.

7.2 PAMGuard Quick View

Each section of the display will show which documents have been exported. For the Detections, this is the separate table in the bottom right of the display, since each

for specific detectors.

module in PAMGuard might be exported to multiple documents. When you select a PAMGuard datablock in the bottom left table, the bottom right table will populate with documents associated with that detector.

You can right click on the appropriate table row and select to view the document, which will open in a new window (Figure 9).




Figure 9: Example of a Deployment document viewed within PAMGuard

You can also use the small down pointing arrow to the right of the **Open Client** button in the connection panel at the top of the display to open lists of all documents in the database, either using the Tethys Client, or in PAMGuard.

Open the Deployment document you created earlier and you will see the information you entered during the export process (Figure 9).

7.3 Delete Exported Documents

As with viewing documents, the same right click actions and the PAMGuard documents list can be used to delete documents.

8 Problems

8.1 Problems exporting

If PAMGuard fails to export a document to Tethys, an error message will appear on the screen. Please copy the text from this message (there is a copy button in the corner of the pop-up window) and send it to us at support@pamguard.org.

Just prior to export, PAMGuard saves a text copy of each document in a temporary folder. This will be something like C:\Users\yourusername\AppData\Local\Temp\PAMGuardTethys. You can find this folder most easily simply by going back to the little menu to the right

of the **Open Client** button and selecting *Open temp folder* from the bottom of the menu. Here you should find a copy of the document that failed to export, (though it may get deleted when you exit PAMGuard). If you can attach that to your email, it will help us to quickly assess what went wrong and try to fix the problem in future releases.

8.2 PAMGuard viewer not finding Tethys data

When you close and re-open the PAMGuard viewer that you exported data from, then if the Tethys server is running PAMGuard should automatically display the documents associated with that dataset. If this doesn't happen, then first open the Client, and check that you can see the documents there. If the documents exist, then the most likely cause is that you've changed the Project name, the Instrument name, or the Instrument Id in the Array Manager all of which are used to associate a PAMGuard dataset with a set of Tethys documents (Section 3).

9 Further Learning

9.1 Tethys

There is extensive documentation for the Tethys Client and the Data Explorer which you should find in both MS Word and PDF format in the Documentation folder of your Tethys Installation. There, you'll also find out about how to import data into R and Matlab. One of the documents is called "READ ME FIRST.docx", so start there.

9.2 PAMGuard Batch Processing

This 'in a Hurry' tutorial has run to over 10 pages, and I'm sure you don't want to go through all of the steps above for every set of data you've collected. The good news is that you probably don't have to. The latest version (2.0 or later) of the batch processor module can run export tasks on multiple PAMGuard datasets fully (or at least mostly) automatically. To learn more about this, complete the latest [Batch Processing](#) and [Batch Output to Tethys](#) tutorials available on the PAMGuard website.

10 Acknowledgements

Funding for this work was provided by the United States [Bureau of Ocean Energy Management](#) under contract 140M0122C0006 (University of Saint Andrews) and Cooperative Agreement M22AC00019-00 (San Diego State University).

